

Wimba Pronto Silent Installation

Wimba Pronto contains a silent installation mode that allows you to install the program more quickly and efficiently than through the standard installation process. Silent Installation installs Wimba Pronto from the command prompt without displaying messages or requiring further interaction. Silent Installation can be useful when:

- Wimba Pronto needs to be installed on multiple computers, such as in a lab setting; or
- Wimba Pronto needs to be installed in a network environment in which the installer resides on a central server and the program is installed remotely.

Note:

Silent Installation mode is only available on computers running Windows and can only be used with Wimba Pronto 2.1 or higher.

To Install Wimba Pronto in Silent Installation Mode

1. Copy the **ProntoSetup.exe** file to the location from which you wish to install Wimba Pronto.
2. Uninstall all previous Wimba Pronto installations.
3. Open a command prompt by selecting: **Start Menu > All Programs > Accessories > Command Prompt.**
4. Type: **c:\[Path to ProntoSetup.exe]\ProntoSetup.exe /S**
(replace [Path to ProntoSetup.exe] with the location of the installer file).
5. Press the **Enter** key on your keyboard. Wimba Pronto is installed via Silent Installation mode.
6. Verify that Wimba Pronto is installed in the following directory:
C:\Program Files\Wimba\Pronto